



SUN 310-875

Exam Name: LEVEL1-FIELD ENGINEER EXAMINATION

Q & A : 140 Q&As

Pdf Demo

Quality and Value for the 310-875 Exam

[Just4Exams Practice Exams](#) for SUN SUN Other Certifications 310-875 are written to the highest standards of technical accuracy, using only certified subject matter experts and published authors for development.

100% Guarantee to Pass Your 310-875 Exam

If you do not pass the SUN Other Certifications 310-875 exam on your first attempt using our Just4Exams **310-875 testing engine and pdf study guide**, we will give you a FULL REFUND of your purchasing fee.

Downloadable, Interactive 310-875 Testing engines and PDF Version

Our Exam Preparation Material provides you everything you will need to take a [SUN Other Certifications certification](#) examination. Details are researched and produced by [SUN Certification](#) Experts who are constantly using industry experience to produce precise, and logical.

Free 310-875 Exams:

This is demo only, this pdf do not include the questions and answers picture

Exam : SUN 310-875

Title : LEVEL1- FIELD ENGINEER EXAMINATION

1. Which sub-command in the format utility will not interfere with Solaris when used to test a disk drive in a booted system?

- A. read
- B. print
- C. write
- D. config

Answer: A

2. How are partitions defined?

- A. size in cylinders
- B. starting cylinder plus ending cylinder
- C. offset from cylinder 0 plus size in cylinders
- D. offset from previous partition plus size in cylinders

Answer: C

3. Which one of the following describes the correct sequence of the system boot phases?

- A. 1st - Boot PROM Phase
2nd - Boot Program Phase
3rd - Kernel Initialization Phase
4th - /sbin/init Phase
- B. 1st - Boot PROM Phase
2nd - Kernel Initialization Phase
3rd - Boot Program Phase
4th - /sbin/init Phase
- C. 1st - Kernel Initialization Phase
2nd - Boot PROM Phase
3rd - Boot Program Phase
4th - /sbin/init Phase
- D. 1st - /sbin/init Phase

2nd - Boot PROM Phase

3rd - Boot Program Phase

4th - Kernel Initialization Phase

Answer: A

4. Which describes physical device names?

- A. They are located beneath the /dev directory.
- B. Entries are created by adding them to the /dev manually.
- C. The command "dmesg" can be used to display physical device names.
- D. They represent the full device pathname in the device information hierarchy.

Answer: D

5. Which is NOT a part of a disk label?

- A. partition tags
- B. volume names
- C. partition layout
- D. file system layout

Answer: D

6. Which statement is INCORRECT?

- A. Logical device names are used to reference devices.
- B. The logical names are located beneath the /dev directory.
- C. The command "prtconf" can be used to display logical device names.
- D. Names are symbolically linked to their corresponding physical device names.

Answer: C

7. Which command is used to delete packages from the system?

- A. pkgm
- B. packagerm
- C. package -d
- D. delpackage

Answer: A

8. Which function is NOT performed by the "format" utility?

- A. disk labeling
- B. creating partitions
- C. creating file systems
- D. repairing defective disk sections

Answer: C

9. What is the correct OpenBoot PROM (OBP) syntax to boot the system to the single-user level?

- A. b -s
 - B. boot
 - C. boot -r
 - D. boot -s
- Answer: D

10. In which file can you find a log of error messages that contain the physical addresses of SCSI peripherals that are producing errors?

- A. /var/disklog
- B. /etc/disklog
- C. /var/adm/logs
- D. /var/adm/messages

Answer: D

11. What is the maximum length of a SCSI-2 single-ended bus?

- A. 5 meters
- B. 6 meters
- C. 9 meters
- D. 10 meters

Answer: B

12. What is the correct syntax for the installboot program?

- A. installboot bootdrive -r
- B. installboot bootblk c0t3d0s0
- C. installboot bootblk /dev/dsk/c0t3d0s0
- D. installboot bootblk /dev/rdisk/c0t3d0s0

Answer: D

13. Which command is used to install patches?

- A. patch -a
- B. patchadd
- C. patches -a
- D. patchinstall

Answer: B

14. Which of the following is an example of the correct /etc/vfstab entry for mounting the /export/home file system at boot time?

- A. /dev/dsk/c0t0d0s7 /dev/rdisk/c0t0d0s7 /export/home ufs yes -
- B. /dev/dsk/c0t0d0s7 /dev/rdisk/c0t0d0s7 /home ufs 2 yes -
- C. /dev/rdisk/c0t0d0s7 /dev/dsk/c0t0d0s7 /export/home ufs 2 yes -
- D. /dev/dsk/c0t0d0s7 /dev/rdisk/c0t0d0s7 /export/home ufs 2 yes -

Answer: D

15. On an Ultra 1, 2, 5, 10, 20, or 60, if an error occurs during post, the Type 5 or 6 keyboard will use the LEDs on the "Caps Lock", "Compose", "Scroll", and "Num Lock" key caps to display the error codes. Which one of the error codes means "No memory found"?

CAPS LOCK COMPOSE SCROLL LOCK NUM LOCK

- A. ON ON ON ON
- B. OFF ON ON OFF
- C. ON OFF ON OFF
- D. OFF ON OFF ON

Answer: C

16. What will the command "test net" do?

- A. performs an ethernet network performance test
- B. performs an ethernet interface external loopback test
- C. performs an ethernet interface internal loopback test
- D. performs an ethernet interface internal/external loopback test

Answer: D

17. Which is NOT a function of the "shutdown" command?

- A. It is used to bring down the system.
- B. It is used to change a system's run level.
- C. It creates a file called /etc/nologin during reboot.

D. It prevents logins by any user except root during shutdown.

Answer: C

18. What Solaris utility is used to repair corrupted file systems?

A. fsck

B. mkfs

C. tunefs

D. prtvtoc

Answer: A

19. Which is NOT one of the fields in the /etc/vfstab file?

A. device to fsck

B. file system size

C. device to mount

D. file system type

Answer: B

20. What data structure describes a unix file system (UFS) layout?

A. label

B. bootblock

C. superblock

D. masterblock

Answer: C

More [310-875 Braindumps](#) Information

Related 310-875 Exams

310-061	310-610	310-230	310-345	310-810
310-600	310-052	310-051	310-620	310-105
310-066	310-203	310-811	310-019	310-330
310-231	412-600	310-062	310-400	310-150

Other SUN Exams

212-083	310-044	310-062	310-813	310-131
212-812	310-013	310-502	212-813	310-879
310-815	310-066	310-220	310-345	212-810
310-051	310-811	310-302	310-610	310-200